README for XFree86 4.0 on OpenBSD

Matthieu Herrb

Last modified on: 20 February 2000

1. What and Where is XFree86?

XFree86 is a port of X11R6.4 that supports several versions of Intel-based Unix. It is derived from X386 1.2, which was the X server distributed with X11R5. This release consists of many new features and performance improvements as well as many bug fixes.

See the Copyright Notice.

The sources for XFree86 4.0 are available by anonymous ftp from:

ftp://ftp.XFree86.org/pub/XFree86/4.0

Binaries for OpenBSD/i386 2.6 and later are available from:

ftp://ftp.XFree86.org/pub/XFree86/4.0/binaries/OpenBSD

A list of mirror sites is provided by ftp://ftp.XFree86.org/pub/XFree86/MIRRORS

XFree86 also builds on other OpenBSD architectures. See section *Building on other architectures* (section 8.2, page 4) for details.

2. Bug Reports for This Document

Send email to <herrb@xfree86.org> (Matthieu Herrb) or <XFree86@XFree86.org> if you have comments or suggestions about this file and we'll revise it.

3. New OS dependent features

See the Release Notes for non-OS dependent new features in XFree86 4.0.

3.1 New OS dependent features in 4.0

- Multi-thread safe libraries are built by default on OpenBSD 2.6 and later,
- Preliminary APM support.

3.2 New OS dependent features in 3.9.18

- Support for USB mices has been added on OpenBSD.
- Soft-booting secondary cards through the int10 BIOS interface is now possible using the x86emu real mode emulator.

3.3 New OS dependent features in 3.9.17

- *Silken mouse* is supported for serial mices, and, under post 2.6 OpenBSD-current for PS/2 mices.
- MTRR Write Combining is enabled under post 2.6 OpenBSD-current.

4. Installing the Binaries

Refer to the Installation Document for detailed installation instructions.

5. Configuring X for Your Hardware

The `/etc/XF86Config` file tells the X server what kind of monitor, video card and mouse you have. You *must* create it to tell the server what specific hardware you have.

You'll need info on your hardware:

- Your mouse type, baud rate and its /dev entry.
- The video card's chipset (e.g. ET4000, S3, etc).
- Your monitor's sync frequencies.

For details about the `XF86Config` file format, refer to the *XF86Config(5)* manual page.

Once you've set up a XF86Config file, you can fine tune the video modes with the `xvidtune` utility.

5.1 About mouse configuration

If your serial mouse does not work try using `kermit` or `tip` to connect to the mouse serial port and verify that it does indeed generate characters.

The OpenBSD pms driver provides both ''raw'' and ''cooked'' (translated) modes. ''raw'' mode does not do protocol translation, so XFree86 would use the **PS/2** protocol for talking to the device in that mode. ''Cooked'' mode is the old BusMouse translation. The driver runs in ''raw'' mode when using the `/dev/psm0` device name.

See README.mouse for general instruction on mouse configuration in XFree86.

6. Running X

6.1 Starting xdm, the display manager

To start the display manager, log in as root on the console and type: ''`xdm -nodaemon`''.

You can start xdm automatically on bootup by changing the line

```
xdm_flags=NO            # for normal use: xdm_flags=""
```

to:

```
xdm_flags=""            # for normal use: xdm_flags=""
```

in `/etc/rc.conf`.

Note that the binary distributions of XFree86 for OpenBSD on ftp.xfree86.org and its mirrors don't include support for the XDM-AUTHORIZATION-1 protocol, because of the US export rules.

6.2 Running X without the display manager

The easiest way for new users to start X windows is to type: "`startx >& startx.log`". Error messages are lost unless you redirect them because the server takes over the screen.

To get out of X windows, type: "`exit`" in the console xterm. You can customize your X by creating `.xinitrc`, `.xserverrc`, and `.twmrc` files in your home directory as described in the xinit and startx man pages.

7. Kernel Support for X

To make sure X support is enabled under OpenBSD, the following line must be in your config file in `/sys/arch/i386/conf`:

```
option XSERVER
option APERTURE
```

7.1 Console drivers

The server supports the two standard OpenBSD/i386 console drivers: pcvt and pccons. They are detected at runtime and no configuration of the server itself is required.

The pcvt console driver is the default in OpenBSD. It offers several virtual consoles and international keyboard support.

7.2 Aperture Driver

By default OpenBSD includes the BSD 4.4 kernel security feature that disable access to the `/dev/mem` device when in multi-users mode. But the XFree86 server require linear access to the display memory in most cases.

OpenBSD now requires the aperture driver to be enabled for all X servers, because the aperture driver also controls access to the I/O ports of the video boards.

To enable the aperture driver, once included in the kernel, set

```
machdep.allowaperture=1
```

in `/etc/sysctl.conf`.

Another (less recommended) way to enable linear memory and I/O ports access is to disable the kernel security feature by adding "option INSECURE" in your kernel configuration file and build a new kernel. You will also need to comment out the line initializing `securelevel` to 1 in `/etc/rc.securelevel`.

> **Caveat:** the aperture driver only allows one access at a time (so that the system is in the same security state once X is launched). This means that if you run multiple servers on multiples VT, only the first one will have linear memory access. Use 'option INSECURE' if you need more that one X server at a time.

7.3 MIT-SHM

OpenBSD supports System V shared memory. If XFree86 detects this support in your kernel, it will support the MIT-SHM extension.

To add support for system V shared memory to your kernel add the lines:

```
# System V-like IPC
options         SYSVMSG
options         SYSVSEM
options         SYSVSHM
```

to your kernel config file.

8. Rebuilding the XFree86 Distribution

The server developer's kit allow you to rebuild just the X server with a minimum amount of disk space. Just unpack it, make the appropriate changes to the `xf86site.def`, type "`./mkmf`" and "`make`" to link the server. See `/usr/X11R6/lib/Server/README` for more info.

You should configure the distribution by editing `xc/config/cf/host.def` before compiling. To compile the sources, invoke "`make World`" in the xc directory.

8.1 Console drivers

XFree86 has a configuration option to select the console drivers to use in `xf86site.def`:

- if you're using pccons only put:

  ```
  #define XFree86ConsoleDefines -DPCCONS_SUPPORT
  ```

- if you're using pcvt only put:

  ```
  #define XFree86ConsoleDefines -DPCVT_SUPPORT
  ```

If you don't define **XFree86ConsoleDefines** in `xf86site.def` the pccons and pcvt drivers will be supported.

8.2 Building on other architectures

XFree86 should also compiles on other OpenBSD architectures. However, please note that 3.9.x snapshots have only been tested on the i386 for now.

9. Building New X Clients

The easiest way to build a new client (X application) is to use `xmkmf` if an `Imakefile` is included in the sources. Type "`xmkmf -a`" to create the Makefiles, check the configuration if necessary and type "`make`". Whenever you install additional man pages you should update `whatis.db` by running "`makewhatis /usr/X11R6/man`".

10. Thanks

Many thanks to all people who contributed to make XFree86 work on *BSD, in particular, **David Dawes**, **Pace Willison**, **Amancio Hasty**, **Christoph Robitschko**, **Nate Williams**, **Rod Grimes**, **Jack Velte** and **Michael Smith**.

CONTENTS

1. What and Where is XFree86? 1
2. Bug Reports for This Document 1
3. New OS dependent features 1
   - 3.1 New OS dependent features in 4.0 1
   - 3.2 New OS dependent features in 3.9.18 1
   - 3.3 New OS dependent features in 3.9.17 2
4. Installing the Binaries 2
5. Configuring X for Your Hardware 2
   - 5.1 About mouse configuration 2
6. Running X 2
   - 6.1 Starting xdm, the display manager 2
   - 6.2 Running X without the display manager 3
7. Kernel Support for X 3
   - 7.1 Console drivers 3
   - 7.2 Aperture Driver 3
   - 7.3 MIT-SHM 3
8. Rebuilding the XFree86 Distribution 4
   - 8.1 Console drivers 4
   - 8.2 Building on other architectures 4
9. Building New X Clients 4
10. Thanks 4

$XFree86: xc/programs/Xserver/hw/xfree86/doc/sgml/OpenBSD.sgml,v 1.10 2000/03/03 21:28:10 dawes Exp $